
Infinite User Management

Print Audit 6 to IUM Migration Guide

Version: 6

Date: 04-Dec-2018 15:42

Table of Contents

Migrating from Print Audit 6 to Infinite User Management (IUM)	2
Install the IUM Server Components	3
Deploy the IUM Client to Workstations	4
Migrate Print Audit 6 data to IUM	5
Remove Print Audit 6 Components	6
FAQ's	7
Does the IUM installer remove the Print Audit 6 Components?	8
Can IUM and Print Audit 6 exist in the same environment?	8
Can I use my Print Audit 6 license key with IUM?	8
Can I keep the Print Audit 6 Components on my server for historical use?	8
Do I need special licensing to use the Database Migration Tool?	8
Can I migrate my current Print Audit Secure server and secured jobs to IUM?	8
Can I migrate my Print Audit 6 data after removing Print Audit 6 from my server?	9

Migrating from Print Audit 6 to Infinite User Management (IUM)

Due to added features and functionality introduced in IUM, upgrading from Print Audit 6 requires some preparation, planning and resource allocation in order to complete a successful upgrade.

- IUM uses a new database structure. Migrating Print Audit 6 data to IUM requires the use of the Database Migration Tool.
- The Print Audit 6 Client and Print Audit Secure Client are not compatible with IUM, requiring the IUM Client be installed on all workstations where tracking or secured printing is required.
- Copy Audit Numeric devices are not supported in IUM. The job data can be migrated from Print Audit 6 but the devices are no longer supported.
- Migration of Print Audit Secure Server configuration and job data is not supported.

Migrating from Print Audit 6 to Infinite User Management may be accomplished through the following steps:

1. Install the IUM Server Components
2. Deploy the IUM Client to Workstations
3. Migrate Print Audit 6 data to IUM
4. Remove Print Audit 6 Components

Install the IUM Server Components

Please refer to the [Print Audit Infinite User Management Installation Guide](#) for full details on installing the IUM Server Components.

Deploy the IUM Client to Workstations

If the Print Audit 6 or Print Audit Secure Client are already installed on the workstation, the IUM Client installer will automatically remove the old clients and will prompt the user for a reboot. If the IUM Client is installed silently, the workstation will automatically reboot without a prompt. The " SuppressReboots" option in the package.ini option will not apply in these cases.

To deploy the IUM Client, please refer to the [Print Audit Infinite User Management Installation Guide](#).

Migrate Print Audit 6 data to IUM

The Database Migration Tool will migrate Client Custom Fields, Printer Profiles, Printer Paper Sizes, Printers, User Profiles and Users from Print Audit 6 to IUM. The Database tool may also be used to:

- Migrate all Print Audit 6 jobs
- Print Audit 6 jobs from a selected date.
- No Print Audit 6 jobs

For more details on using the Database Migration Tool, please refer to the [Infinite User Management Migration Tool](#) documentation.

Remove Print Audit 6 Components

The IUM does not automatically remove Print Audit 6 Components that may be installed on a server. You may use "Uninstall a program" in the Control Panel to remove all of the Print Audit 6 components from the server or use the Print Audit 6 installer to remove selected components from the server.

FAQ's

Does the IUM installer remove the Print Audit 6 Components?

Yes and No.

Yes - when installing the IUM Client to a workstation, the Print Audit 6 and/or Print Audit Secure Client will be removed and replaced by the IUM Client.

No - the IUM installer does not remove the Print Audit 6 Administration and Reporting Components.

Can IUM and Print Audit 6 exist in the same environment?

IUM and Print Audit 6 server components may run together in the same environment or even on the same server. However, the IUM Client and the Print Audit 6 Client/Secure Client CANNOT reside on the same workstation. The Print Audit 6 and Print Audit Secure Client are not compatible with IUM.

Can I use my Print Audit 6 license key with IUM?

No. The Print Audit 6 and IUM License keys cannot be interchanged. If upgrading from Print Audit 6 to IUM, you will need a new IUM license key.

Can I keep the Print Audit 6 Components on my server for historical use?

Yes. The Print Audit Administrator and Job Reporting tools may be kept and used to access any Print Audit 6 database if desired.

Do I need special licensing to use the Database Migration Tool?

No. The Database Migration Tool is included with IUM and does not require any special licensing.

Can I migrate my current Print Audit Secure server and secured jobs to IUM?

No. Currently, any print jobs secured with Print Audit Secure Server/Client will need to be released through Print Audit Secure.

Can I migrate my Print Audit 6 data after removing Print Audit 6 from my server?

Yes, provide that the Print Audit 6 database (Access or MS-SQL) has not been removed yet.